

Paraview GUI commands

🕒 Created	@May 18, 2022 10:48 AM
🏷️ Tags	

How to use Python macro

1. load macro
2. check the macro is added in Paraview. You should see a new button with the name of the macro function on it.
3. press the button and run the macro

List of Macro

visualiseVTK.py - takes vtk or vtk.series file and creates tensors glyphs with color

Parameters to adjust

particle size

Particle size is determined by $Radius \times ScaleFactor$

resolution

Resolution defines how many points are used to plot an ellipsoid. There are 2 parameters, theta and phi.

Total number of points on an ellipsoid: $\theta \times \phi - (\phi - 1) \times 2$

color

background, axis grid, etc - you can adjust background color by clicking "color palette icon"



Video

To use the “time inspector feature” in Paraview, the file needs to be in vtk.series format. vtk.series is simply a json with the name of the file and the timestep it corresponds to.

```
≡ ellipsoids.vtk.series
1  {
2    "file-series-version" : "1.0",
3    "files" : [
4      { "name" : "data/Fig1E.vtk", "time" : 0 },
5      { "name" : "data/Fig1F.vtk", "time" : 1 },
6      { "name" : "data/Fig1G.vtk", "time" : 2 },
7      { "name" : "data/Fig1H.vtk", "time" : 3 }
8    ]
9  }
10
```

The program uses sort() to sort the files in the directory by their names and put them into a vtk.series file in ascending order.

Users can change the order of vtk files, time manually presented in vtk.series.

save animation

<https://docs.paraview.org/en/v5.8/UsersGuide/savingResults.html#:~:text=To save an animation as,and which format to use.>